


Remote Support & Management PC – Mac – Tablet – Smartphone – Embedded device

WiseMo Guest module
on your iPhone / iPad



WiseMo Host module
on your computer or device



1. An Introduction

WiseMo develops software for remote control between computers and devices, for example between PCs, Servers, Mac computers, Smartphones, Tablets, and other handheld or un-attended devices. Using WiseMo software you have a powerful set of remote control and management features available to increase your efficiency – saving you time and money.

Guest & Host modules

The WiseMo Guest module runs on the computer or device from where you want to access and take remote control of other computers and devices.

The WiseMo Host module runs on computers and devices to prepare them for access by users with a Guest module.

Cloud & On-premises connectivity:

Connection between the Guest module and the Host module is either established via WiseMo's myCloud connectivity over the Internet or directly using TCP/IP communication on a LAN/WAN network managed by you.

For Cloud connectivity (WiseMo myCloud), your computer or device must be able to use the Internet, for example via fixed line, Wi-Fi or mobile operator network (3G, 4G, etc.). This will allow you to reach a computer or device wherever it may be and from wherever you are – as long as there is Internet connectivity on both the Guest and Host.

By using TCP/IP directly between Guest and Host computer on your own network (e.g. your Wi-Fi, LAN or WAN) you can avoid Internet traffic and possible data charges from your mobile operator.

The iOS Guest app, for iPhone and iPad

This guide provides information on how to install, configure, use and uninstall the iOS Guest app – our Remote Desktop Guest module for use on iPad and iPhone devices for efficient remote control of computers and devices running a WiseMo Host module.

IMPORTANT: This guide assumes that you have at least one WiseMo Host module installed on a computer or device, ready to be reached, either via myCloud connectivity or directly via TCP/IP. For information on how to setup a Host module, please refer to the tutorials for such module. Available documents can be found here: <http://www.wisemo.com/support/documents/>




WiseMo develops cloud based and premises based remote control software for use between computers and devices, e.g. between PCs, Servers, Mac, Smartphones, Tablets, and other handheld or un-attended devices. Our cross platform solutions target the commercial and industrial remote support and management (RSM) market.

For more information, see www.wisemo.com.

2. Installation of the iOS Guest app

The app is installed on your iPhone or iPad so you can reach and remote control PCs, Servers, Mac, Smartphones, Tablets or other handheld or un-attended devices. The app requires iOS version 8.0 or later versions.

Download the app from App Store:




After download, open the app, either from App Store or by finding the Guest icon on your device.

3. The Start-up Wizard

The first time you run the app, you will be met by the startup wizard. It introduces you to myCloud and permits you to pre-configure the use of a specific myCloud domain, if you already have access to one. It also provides you with a link to create a trial myCloud domain, if you wish to try easy connectivity over the Internet

If you initially just want to use the Guest on your own network, just press the Continue buttons and you will reach the Guest user interface. You can later easily log on to a myCloud domain directly from the user interface or enable the Wizard to run again.

Other configuration options are found in the Options tab, which dictates the default connection properties used when connecting to a remote computer or device. Individual Connection Properties can be defined via the Phonebook tab.



4. Using the Guest app

It is assumed that you have at least one WiseMo Host module running on a computer or device, so you are prepared to successfully initiate a remote desktop control session.

The Guest is organized into tabs, shown at the bottom:



On an iPad, the tabs are using a split-view lay-out, while for an iPhone, you may need to tap an item to see the details view.




In general, if you are one level down, you can press the "back" button in the upper left corner to move one level up.

You are at the top level when you do not see any "back" button.

We will cover each tab below. If you want to make your first remote control connection via TCP/IP, for example to another computer or device also available on your local Wi-Fi or LAN, you can go directly to 4b – The Quick Connect tab.


4a. The myCloud tab




If you are logged into a myCloud domain, you will see a list of your myCloud enabled Host computers and devices.

From this tab you can easily select and connect to the computers and devices you want to reach. You can choose to start a remote control (Remote Desktop) or a chat session (Chat).

(Remember, you need at least one Host module enabled for your myCloud domain, to see any Hosts listed in the myCloud tab)



Notice the Search field. The list of enabled computers and devices will show only those entries that match your entry in the search field – very handy when you have large quantities of hosts enabled for a domain.





The list of myCloud enabled computers and devices is automatically updated, appx. every 10 seconds, as computers and devices enter the domain, or when mycloud is aware a host has left the domain or changed its status. You can manually refresh the list of hosts – just press the refresh button, found top right in the list view.



If already logged on, use the log-off button, found at the top left, to leave the domain, for example if you want to log-on to another domain.



If you are not logged on, press the refresh button, found top right. This will take you to the log-on screen.




Enter your myCloud user account credentials, (email and password) and press the "Log on" button.

The program can remember your credentials, so you do not need to re-enter those, each time you start the Guest app. Use the Remember password switch to control this.

*Example: Remote Desktop Control of an Android device from an iPhone.
The screen of the Android device is shown on the iPhone device*



Full screen view



Pinch with 2 fingers to zoom

Please refer to [5. Remote Control of a Host computer or device](#) for information on options available during a remote desktop control session

4b. The Quick Connect tab



Use this tab to quickly connect via TCP/IP to a computer or device running the WiseMo Host module.

You need to know the IP address of the distant Host (or the full DNS name) and it must be reachable via TCP/IP communication, for example if both are on the same LAN or Wi-Fi.

Simply enter the address and press the Connect button.

Make sure TCP/IP is selected as the Communication Profile.

You can choose between establishing a Remote Desktop or a Chat session:




Notice: A connection will use the default connection properties defined in the Options tab. You can define individual connection properties if you use the Phonebook tab. Connection properties allows you to automate the entry of log-on credentials, select how the remote desktop screen is presented (full / actual size) and many other options.

Notice: As default, the program uses port 1970. If the Host module on the target computer is setup to listen at another port, you can specify such port in the Host ID field, after the IP address. For example specify: 10.204.1.3:1975 where 1975 is the port.

Share links and Invitation links

If someone has sent you a Share link or an Invitation link, you can paste it into the Host ID field, and press the Connect button. The Guest will connect via myCloud to the Host for which the link was created. This requires your device is Internet enabled!

Example: Remote Desktop Control of Windows 10 PC from iPhone



Full screen view



Pinch with 2 fingers to zoom

Please refer to [5. Remote Control of a Host computer or device](#) for information about options available during a remote desktop control session



Quick Connect History

The addresses used are saved in the Quick connect history list, so it is easier to re-connect to previously connected Hosts. To reach the Quick connect history list, click on the > button:



From the Quick connect history list, you can add the Host to the Phonebook using the Add button:

Add to phonebook



4c. The Phonebook tab




From the phonebook tab, you can create Host entries with pre-defined address and Connection Properties.

Phonebook Select a Host from the list and click Remote Desktop or Chat to connect.

In the Phonebook list, you can see which Hosts you are connected to, and you can easily choose the session type you want, Remote Desktop or Chat.


You can also disconnect already connected hosts.



Click the + button found top left, to add a new Host entry to the Phonebook

Each Host defined in the phonebook can have individual connection properties, so you can tailor the best settings for an optimal connection.

As a minimum, you must enter a Description and a Host ID. The Host ID could be the IP address of the distant Host computer. All other settings will be the default settings, which you can change now or later, to match your preferences for connection to this specific Host.



To save the new entry, press the "back" button found top left in the details view.




To remove a Phonebook Host entry, first tap the "Garbage" button top right, then tap the red button in front of the Host entry you want to delete, and tap the "Delete" button to confirm. When you are done deleting phonebook entries, tap the button "Done".

Please notice that you may have different views depending on the type of device and whether your device is in landscape or portrait mode.

Example: Remote Desktop Control of Window CE device from Guest module on an iPad

Drop-down screen for passing special keystrokes to the Host computer.

Notice the special buttons on the top menu for control of Windows Mobile/CE devices. On narrow screens, these are shown in the drop-down screen.



4d. The Connections tab




The Connections tab lists all current connections, irrespective of whether the connections have been established from the myCloud tab, the Quick Connect tab or from the Phonebook tab.

From the Connections tab you can jump between already connected Host computers and devices.

For an already connected Host, for example with a Remote Desktop connection, you can initiate a Chat session, and vice versa.

You can also disconnect Hosts via the Connections tab.



Notice that the Connections tab name includes the number of current connections, a quick way to see if you have any connections.

4e. The Options tab





The Option tab allows you to change the default Connection properties, used when connecting to a remote computer or device. The Option tab also provides various other settings and information.

1. Connection Properties

Connection properties are used when you connect to a remote Host computer from the myCloud tab or the Quick Connect tab. These properties are also used as default settings when adding a Phonebook entry. Each type of setting is described below.

1a. Host Log On Credentials

Pre-define credentials, such as user name, password and domain or workgroup. These settings are used to automate log on to a Host. If the credentials are wrong or missing, the Guest will prompt you for missing credentials upon connection to the Host.




1b. Display

Size to full screen:

Check this, if the Guest initially should show the desktop of the Host completely. While connected, you can resize it to show only part of the desktop, but in greater detail.

Un-check this and the Guest will initially show the remote desktop in its actual size, typically resulting in only part of the screen being shown. While connected, you can easily move around to see all parts of the desktop or size to see the full screen.



Picture Quality:

Use the "slider" to choose between quality of screen and speed of screen transfer. If you communicate via a slow link, you benefit from sacrificing a little bit of quality – while if you run on very fast lines, you will perhaps want the best possible screen quality. A middle position is often the best option when working over the Internet.


1c. Desktop Optimization

These settings dictate how the screen on a distant computer is modified during connection, to ensure best possible performance.

Optimize: Defines if optimization should be attempted or not
All features: Check this to use all optimization features possible

You can disable specific optimizations features, you do not wish to use. The features are:

Wall paper: Removes the wallpaper on the remote screen
Screen saver: Disables screen saver
Animation gimmicks: Disables various animation gimmicks the remote desktop may otherwise use.
Full window drag: When dragging a window, only the frame is shown, not the window content.
Active Desktop: Disables use of the Active Desktop, found on older Windows PCs
Aero: Disables the use of Aero (e.g. see through window frames)



Whether an optimization is actually used, depends on the Host operating system and the version of the operating system.

1d. Keyboard and Mouse

The "Open at startup" setting opens the Guest keyboard automatically, when connected to a Host.

The "Show extended keyboard" will add a top row of keys to the keyboard on the Guest device. This includes special key buttons, for example function keys F1, F2, etc. You can scroll this row of buttons, for example on an iPhone, where the device cannot show all of them at the same time.

1e. Compression

You can define High, Low or not to use compression at all. Normally best option is to maintain the Automatic setting. The settings define how much the data transferred is compressed. High compression uses more CPU power, but less data need then to be transferred.

1f. Preferred encryption

The settings of the Host ultimately dictates which encryption settings can be used. However, as a Guest user, you may state your preference, and if permitted by the Host, your preference will be used. Otherwise, an encryption level permitted by the Host will be used.

1g. Startup Actions

This is settings that automate actions upon connection with the Host, subject to the Host security settings permitting such action.

- Lock keyboard and mouse: The user on the Host PC will not be able to use his keyboard and mouse, while the Guest is connected.
- Blank screen: The screen on the Host PC will be blanked, so what you are doing cannot be viewed on the Host.
- Suspend other Guests from Connecting: With WiseMo products, multiple Guests can be connected to the same Host, if permitted. This setting ensures that no other Guest is allowed to connect while you are connected.

2. myCloud account


myCloud is used for trouble free connectivity over the Internet. When logged on to a myCloud domain, you will, in the myCloud tab, see a list of your myCloud enabled Host computers and devices.

You log on to a myCloud domain by specifying your myCloud user account and credentials. From this screen, you can pre-define your log-on credentials, and verify that they are working.

(The URL field should be left untouched).

“Log on at startup” will result in automatic logon to the myCloud domain defined by the credentials specified above.


“Configure at startup” will launch the Setup Wizard when the Guest app is started.




3. About

The About screen provides various information about the program and the device itself, including version, licensing and copyright notices.

4. Mouse Gesture Instructions



To simulate the use of a traditional mouse on the remote Host computer, the Guest program uses a Mouse Marker. It is also used for positioning and executing mouse actions on remote devices. The marker consists of the square area indicated by the 4 corners, and a mouse pointer.



Read the Mouse Gesture Instructions to learn how you use the marker for left click, right click, vertical scroll and many other useful actions.

5. Save Communication Log

Save a log file with lower level communication between Guest and Host. Used for trouble shooting reasons. If you need to report a problem, WiseMo support may request that you create this log and send it to us. Make sure you have an enabled email account on your device, save the communication log, and you will be able to email the log.

5. Remote Control of a Host computer or device

When connected to a Host computer or device, you will see the remote desktop, or part of it, on the screen of your device. You can easily adjust the visible part of the desktop by pinching with two fingers on it.



 Use gestures or the re-sizeable WiseMo mouse marker on your device to work on the screen of the remote Host computer or the remote Host device (you can learn about the gestures from the Options tab / Mouse Gesture Instructions).

Menu buttons

The top menu provides various buttons. Some buttons work locally on the Guest app, others are special buttons, which vary depending on the Host type you are connected to. The special buttons are executed on the remote Host.

 Press this button to go back to the Tab view you came from. This does not terminate the session!

 Press this button to terminate the session with the Host.

 This button shows a screen with special buttons to send keystrokes to the remote Host computer or device. One example is passing of Ctrl-Alt-Del often needed on Windows PCs, another example is the Home button often used on Android devices.

 This button shows a menu of commands for executing specific features, depending on the capability of the Host computer / device. Features includes launch of marker mode, lock keyboard / mouse, restart, lock or log-off the Host computer, send / receive clipboard.

  Open / (close) the Guest keyboard on the iPhone / iPad

 Press this button to access the Mouse Gesture Instructions.


 Special buttons you can execute on remote Android Host devices. They are shown in the top menu, when space permits (iPad).

 Special buttons you can execute on remote Win Mobile/CE Host devices. They are shown in the top menu, when space permits (iPad).

Mouse marker

The mouse marker consists of a frame indicated by 4 corners, and a mouse pointer in the middle. Tap outside the frame to position the mouse, move finger inside the frame to adjust the position, tap inside the frame to execute a mouse click.

For remote desktop control of a Host, the mouse pointer on the Guest will dynamically change to reflect the situation on the remote Host computer. Here are a few examples of different mouse pointers:



You can easily re-size the mouse marker, to obtain a size that works best for you. Pinch inside it with two fingers.

Mouse gestures

From the Guest Options tab you can always check the Mouse Gesture Instructions, for help on gestures available to you.

 Pan screen Move finger outside mouse.	 Move mouse Move finger inside mouse.	 Click mouse and hold Tap twice and hold the second time inside the mouse. Do it with two fingers for right mouse button.
 Zoom screen Pinch with two fingers.	 Left mouse click Tap finger inside mouse. Tap twice to double click.	
 Position mouse Tap outside mouse frame to re-position mouse.	 Right mouse click Tap two fingers inside mouse. Tap twice to double click.	 Vertical Scroll Position two fingers inside the mouse and move them up and down.

Pop-up screens

When connecting to Host computers and devices you may, depending on the settings on the Host, be required to fill in password credentials or wait for someone on the Host side to grant or deny you access.

Host log on

User name
Password
Domain

Cancel Log on

Confirm Access

Waiting for Host user to Confirm Access

Cancel

Confirm Access

Confirm Access denied by Host

Ok

Multiple Guests connected to the same Host

Multiple Guests can simultaneously connect to the same Host – if permitted. This allows for multiple Guest users to follow what is happening on a single remote desktop.

While all Guest users will be able to view the screen, only one Guest at a time will have control of the Host's keyboard / mouse / input controls. The Guest that first connects will initially have the input control.

Any Guest user can take the input control by passing an input action on to the Host, like a click with the mouse. This results in a notification that "Input has been assigned" after which, any following input action will take place on the Host. The Guest user that had the input control will receive the notification: "Input revoked by Host".

6. Share links and Invitation links

If someone has sent you an Invitation link (from a specific Host) or a Share link (from the myCloud web interface) you can paste the link into the Host ID field, and press the Connect button. The Guest will connect via myCloud to the Host for which the link was created – and that without you needing to be logged into such myCloud domain. This requires your device is Internet enabled.

7. Uninstalling the Guest app

Uninstall the Guest app in the usual way you uninstall apps on your device. For example, long press on the Guest icon on your device, and then press the X on the Guest icon.

8. License information for the Guest app

The iOS Guest module, version 17 comes with a free perpetual license to use on all your supported iPhone, iPad or iPod devices.

From the Guest module you may connect to validly licensed WiseMo Host modules.

9. Glossary

Computer – Any Server, Workstation, Desktop, Laptop that runs an operating system supported by the Guest or Host module.

Device – Any Smartphone, Tablet, Set-top box, Scanner, or other handheld or un-attended device that runs an operating system supported by the Guest or Host module.

Guest – the module installed on a computer or device, e.g. PC, on an iPad, iPhone, Android device or running from a supported Browser. From the Guest module, the user may remote control another device or computer where the Host module is running.

Host – the module installed on the target computer or device that should be remotely controlled from the Guest module. It can for example be a PC, Mac, Smartphone, Tablet, Set-top box, or any other type of device that runs a supported operating system.

Host Configuration Manager – also termed Mobile Host Manager. A tool used for configuring a WiseMo Host application. It is installed on a Windows desktop computer and communicates with your device when the device is USB connected to your PC.

Skin – the graphical user interface for remote control of devices. Usually it is almost an exact graphical copy of the real device which is being remote controlled. Skin buttons are "alive" and imitate the keystroke of the real button: if you click on one of them then the same action will be performed on the device as if you click the real button.

Communication profile – protocol configuration for the communication between a Guest module and a Host module. There are two main communication methods: TCP/IP and myCloud. Before

connecting directly from a Guest to a Host you should specify on the Guest which communication profile should be used.

myCloud – one of the communication profiles. myCloud communication is an internet based protocol that allows connection through firewalls, proxies and NAT'ed networks. It comes as part of WiseMo's myCloud subscription based service for easy remote control connectivity between computers and devices.